

- Contents -

1. Cautions for Installation
2. Cautions for Removal
3. Changes in the Service Pack
4. Cautions for Use
5. License Agreement for Built-in Software

- High Safety Required Use -

This Product is designed, developed and manufactured as contemplated for general use, including without limitation, general office use, personal use, household use, and ordinary industrial use, but is NOT designed, developed and manufactured as contemplated for use accompanying fatal risks or dangers that, unless extremely high safety is secured, could lead directly to death, personal injury, severe physical damage or other loss (hereinafter "High Safety Required Use"), including without limitation, nuclear reaction control in nuclear facility, aircraft flight control, air traffic control, mass transport control, medical life support system, missile launch control in weapon system.

If user does not perform secure measures required in assuring High Safety Required Use, user shall NOT use this software. Pfu Limited and related companies accept no claims from customers and third parties in relation to, and accept no responsibility for any losses incurred as a result of, the use of this software for High Safety Required Use.

1. Cautions for Installation

=====

- * The following languages are supported for this product.
English, French, German, Italian, Spanish, Chinese (simplified), Korean, Japanese
- * This product is designed to work on following operating systems.
Windows(R) 2000 Professional (Service Pack 4 or later) (*1)
Windows(R) XP Professional (32-bit version only) (*1)
Windows(R) XP Home Edition (*1)
Windows Vista(R) Home Basic (32-bit and 64-bit versions)
Windows Vista(R) Home Premium (32-bit and 64-bit versions)
Windows Vista(R) Business (32-bit and 64-bit versions)
Windows Vista(R) Enterprise (32-bit and 64-bit versions)
Windows Vista(R) Ultimate (32-bit and 64-bit versions)
Windows(R) 7 Starter (32-bit version)
Windows(R) 7 Home Premium (32-bit and 64-bit versions)
Windows(R) 7 Professional (32-bit and 64-bit versions)
Windows(R) 7 Enterprise (32-bit and 64-bit versions)
Windows(R) 7 Ultimate (32-bit and 64-bit versions)

(*1) For Windows(R) XP, Service Pack 2 or later is required for using the following linkable functions.

Operation is not supported by Windows(R) 2000.

- Evernote
- Google Docs(TM)
- Salesforce Chatter
- SugarSync
- iPad/iPhone/iPod touch

- * To install this product, please login as Administrator or a member of

Administrators Group (or as a user having administrative right).

- * Before beginning the installation, end all applications and turn off any antivirus software.

2. Cautions for Removal

=====

- * To uninstall Rack2-Filer, log in as the user who installed Rack2-Filer. Administrators privilege is required for the user.
- * Exit all applications and antivirus software before uninstalling Rack2-Filer.
- * Before installing a previous version of Rack2-Filer, uninstall the current version from the Windows [Control Panel].

3. Changes in the Service Pack

=====

V5.0L60a is the same as V5.0L10, V5.0L11, V5.0L31a, V5.0L40a, V5.0L41a, V5.0L51a or V5.0L52a which have Service Pack 5 applied.
The main contents changes are as follows.

- * Added the "Photo Binder" function for specifically managing photos.
- * Added the function for exporting binder data as a PDF file to Evernote, Google Docs(TM), Salesforce Chatter, SugarSync and iPad/iPhone/iPod touch.
- * Added the method of importing 8 cards per page (left and right side of the page) to the former method of importing 4 cards per page (left side of the page) when importing to a card binder.
- * Improved the efficiency of the process of deleting sheets or pages.
- * Improved the page turning position, so that the page is not mistakenly turned when selecting a page in Rack2-Viewer.
- * Corrected the problem of long processing times when running OCR on data containing detailed table formatting.
- * Corrected the problem of the selected area not being zoomed as selected when zooming an area in Rack2-Viewer.
- * Corrected the problem of the displayed image becoming blurred in environments using multiple displays when maximizing the window in Rack2-Viewer.
- * Some other minor problems have been corrected or improved.

V5.0L52a is the same as V5.0L10, V5.0L11, V5.0L31a, V5.0L40a, V5.0L41a, or V5.0L51a which have Service Pack 4 applied.
The main contents changes are as follows.

- * Corrected the problem of the date range specification not functioning when using the search binder function on the Rack2-Filer window.
- * Corrected the problem that the changing of the order of pages on a contents page does not apply correctly.
- * Corrected the problem that high resolution files and files imported with Rack2-Viewer in compact mode are displayed on Rack2-Viewer with a grainy resolution.
- * Corrected the problem that a personal computer with a CPU that does not

support SSE2 could not run OCR correctly.

- * Corrected the problem of the CPU utilization rising to 100% when running OCR.
- * Corrected the problem of PDF data created with Rack2-Filer being displayed as reversed black and white on Adobe Reader and Adobe Acrobat.
- * Some other minor problems have been corrected or improved.

V5.0L51a is the same as V5.0L10, V5.0L11, V5.0L31a, V5.0L40a or V5.0L41a which have Service Pack 3 applied. The main contents changes are as follows.

- * Corrected the problem of the binder not saving properly in Rack2-Viewer if antivirus software was installed.
- * Corrected the problem of a stack not being able to be moved from WorkArea to Rack2-Filer or Rack2-Viewer.
- * Corrected the problem of the binder taking too much time to display in Rack2-Filer.
- * Corrected the problem of the modified contents of a sheet (source file) not being applied to the sheet in Rack2-Viewer.
- * Corrected the problem of the card binder not saving properly if antivirus software was installed.
- * Corrected the problem of Internet Explorer not printing with Raku2 ImageWriter if Protected Mode was enabled for Internet Explorer.
- * A binder created in the later version of Rack2-Filer can be edited.
- * Now supported for ScanSnap S1100.
- * Corrected the problem where saved data could not be viewed in explorer if the data storage destination or the data export destination on Windows(R) 7 is set directly below the system drive.
- * Corrected the problem of an image distorting after editing a source file with Rack2-Viewer.
- * Corrected the problem where printing failed to complete when printing many pages with Rack2-Filer or WorkArea.
- * Corrected the problem of files not being imported when multiple Microsoft(R) Excel(R) sheets with different resolutions were imported to Rack2-Viewer.
- * Corrected the problem of importing being prevented by an error occurring when a certain type of PDF file was imported to Rack2-Viewer.
- * Corrected the problem where an error occurred when Rack2-Viewer was started if the default printer had a long name.
- * Some of other minor problems have been corrected or improved.

V5.0L41a is the same as V5.0L10, V5.0L11, V5.0L31a or V5.0L40a which have Service Pack 2 applied. The main contents changes are as follows.

- * Corrected the problem of the binder spine turning white when importing data from the Print menu of other applications or Rack2 Folder Monitor Software into Rack2-Filer.
- * Corrected the problem of the default printer printing out if files were inserted from Rack2-Viewer or Rack2 Folder Monitor Software on

Windows (R) 7.

- * Corrected the problem of an error occurring when an annotation was added or when [Right Rotated], [Left Rotated], [Pages From File], or [Cycle Pages] is performed if Fullscreen was set in the Window Mode of Rack2-Viewer settings.
- * The following problems for Rack2 Folder Monitor Software have been corrected.
 - Corrected the problem of monitoring the monitored folder for a shorter interval than the Check folder every set in Rack2 Folder Monitor Software.
- * Some of other minor problems have been corrected or improved.

V5.0L40a is the same as V5.0L10, V5.0L11 or V5.0L31a which have Service Pack 1 applied. The main contents changes are as follows.

- * Now supported for Windows (R) 7.
- * Now supported for ScanSnap S1300.
- * All set LibRoot folders are displayed in the folder view and binders in the LibRoot folders can be moved or duplicated.
- * Increased the number of sheets that can be managed in the WorkArea at one time for functions such as file import or marked text crop, from 500 to 1000.
- * Fixed the problem that when searching a binder, the keyword information was not correctly searched for.
- * Fixed the problem that when scanning multiple business cards with a flatbed scanner, the business cards scanned first were imported to Rack2-Viewer multiple times.
- * Fixed the problem that pages after the second page could not be viewed when exporting a password protected binder with "Rack2 Binder with embedded Viewer (*.exe)", and then opening it without Rack2-Viewer being installed.
- * Corrected the problem that when a sheet smaller than A4 size was imported to Rack2-Viewer, it was zoomed in when displayed.
- * Corrected the problem that import was not possible when a binder containing sticky notes that was created with a version of Rack2-Filer prior to V5.0, was specified as the Target Binder of Rack2 Folder Monitor Software or the binder to which data is sent from another application.
- * Corrected the problem that in a library with multiple cabinets with long names, changing the background operations failed, and cabinet deletion was not possible.
- * Corrected the problem of the binder not opening when the password-protected binder was edited if the LibRoot folder was set in the network.
- * Some of other minor problems have been corrected or improved.

V5.0L31a is the same as V5.0L10, or V5.0L11 which have Update Pack 2 applied. The main contents changes are as follows.

- * Corrected the following problems that occur only with Windows (R) 7.
 - Corrected the problem that when "Color" is set in the Preferences for Raku2 ImageWriter, and a document is printed from Rack2-Viewer

or the WorkArea, the colors are sometimes inverted.

- Corrected the problem that when a Standard user logs on, files cannot be inserted to Rack2-Viewer or imported to the WorkArea.
- Corrected the problem that when the left and right pages of an open binder are contents pages, there is a delayed response when the edge of a page is clicked.
- * Corrected the issue of an error occurring when the first item in the contents list is moved to an even numbered page in the contents list using the "Paste Contents" operation.
- * Corrected the issue of excessive time delay between the time when the [Scanner] button in the Rack2-Viewer window is clicked and when the scan actually starts (or TWAIN driver window appears) during document scanning using a FUJITSU fi series scanner with TWAIN driver.

V5.0L11 is the same as V5.0L10 which have Update Pack 1 applied.
The main contents changes are as follows.

- * Problem that key text blocks may be created over again depending on the page layout is improved.
- * Problem that an application error occurs when scanning data with a scanner with TWAIN driver, and importing the scanned data into a new binder, scanning more data, saving the data, and exiting the Rack2-Filer, is corrected.
- * Problem that pages cannot be flipped smoothly with some pointing devices is corrected.
- * Problems when Rack2-Filer is installed with some types of file encryption software are corrected.
- * Corrected the problem that in some computer environments, the activation message appears at program startup, even after activation has already been performed.

4. Cautions for Use

=====

- * When setting a LibRoot folder in the network folder and sharing the data, the font specified as the binder title may not be displayed correctly if the client computer does not have the required font.
- * Rack2-Filer may not operate correctly under virtual environments such as remote desktop.
- * Do not log off or shutdown while an operation is being processed in the WorkArea.
- * If the characters on the screen for Windows are set to be zoomed in, some of the Rack2-Filer screens may not be shown correctly with the resolution other than 1024 x 768. In this situation, set the size of the characters to the standard setting.
- * Environment dependant characters (unicode) are not supported. Do not use environment dependant characters (unicode) for the installation folder, user names, folder names, and other string variables.
- * PDF files created with ScanSnap on a Mac OS cannot be used as "Data scanned with ScanSnap" in Rack2-Filer. For this reason, functions for "Data scanned with ScanSnap", such as "Crop marked section" and "Output to Office", cannot be used with imported pages of these types of PDF files.

* Do not specify a LibRoot or a folder under a LibRoot as your SugarSync folder. Synchronization of binder data is not supported.

5. License Agreement for Built-in Software

- GData .NET Client Library
Google.Gdata.Client.dll has been partly modified then built in.

According to the license agreement for the built-in software above, the license statements are given as follows:

Copyright PFU LIMITED 2011

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

Microsoft, Windows, Windows Vista, Internet Explorer and Excel are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Evernote is a registered trademark or trademark of Evernote Corporation.

Google and Google Docs are registered trademarks or trademarks of Google Inc

Salesforce, the Salesforce logo, and Salesforce CRM are registered trademarks or trademarks of salesforce.com, inc. in the United States and other countries.

Other company names and product names are the trademarks or registered trademarks of the respective companies.

Copyright PFU LIMITED 2006-2011