PaperStream IP (TWAIN) for SP Series change history

Version 3.2.1

New features:

 Added a function to automatically correct the orientation of the image based on the pre-registered information on the reference area for detecting the document orientation.

This enables the document orientation to be corrected for images whose orientation cannot be corrected even when [Automatic] is selected for [Rotation] in [Page].

Select the [Use custom rotation settings] check box to enable this function.

2. Added a function to automatically detect a passport when scanned on a flatbed.

This function is available with PaperStream Capture.

Improvement:

- 1. The scanner driver window has been renewed.
 - Added some setting items in the Simple dialog.
 - Improved the visibility and the accessibility of the setting items.

Version 2.14.2

Corrected issue:

- 1. Fixed the problem in which the following symptoms occur when the document is skewed by nearly 45 degrees during a scan.
 - Insufficient memory error is displayed
 - Image is output with large amount of blank spaces
 - Driver hangs

Version 2.14.1

Improvement:

 Removed the limit on the number of allowable PaperStream IP installations from EULA so that a scanner can be shared.

Corrected issues:

- 1. Fixed the problem that occurs when Automatic Profile Selection is used in a general user environment, preventing specific document information from being added.
- Fixed the problem in which opening and closing the cover is required for closing the error that occurs when a scanner failed to pick a paper to scan.
- Fixed the problem that may occur in which, even when the style of a
 document is recognized to be identical to specific document information,
 the resolution specified in the normal dialog of PaperStream IP is applied
 for the document.
- 4. Fixed the problem in which Software Operation Panel does not occupy the connected scanner while allowing its device settings to be configured.

Improvement:

 Removed the limit on the number of allowable PaperStream IP installations from EULA so that a scanner can be shared.

Corrected issues:

- 1. Fixed the problem that occurs when Automatic Profile Selection is used in a general user environment, preventing specific document information from being added.
- Fixed the problem in which opening and closing the cover is required for closing the error that occurs when a scanner failed to pick a paper to scan.
- Fixed the problem that may occur in which, even when the style of a
 document is recognized to be identical to specific document information,
 the resolution specified in the normal dialog of PaperStream IP is applied
 for the document.
- 4. Fixed the problem in which Software Operation Panel does not occupy the connected scanner while allowing its device settings to be configured.

Version 2.12.3

Corrected issue:

- 1. Fixed the problem that occurs when a scan is performed under the following conditions, causing abnormal end or hangup of the scanning application.
 - Driver: PaperStream IP for SP (TWAIN/TWAIN x64) 2.12.0
 - App: PaperStream Capture, or an app that shows no driver window during scan
 - User: No administrative privileges

V2 Service Update 1

Version 2.12.0

New features:

- 1. Windows Server® 2008 Standard has been removed from supported OS list.
- 2. Automatic Profile Selection has been added.
- 3. Through our unique image processing technology, it now outputs black and white images which are appropriate for OCR processing.
- 4. Software Operation Panel Energy Star® 3.0 is now supported. The maximum period of time which the scanner automatically moves to power saving mode has been changed from 235 to 115 mins.

Service Update 8

Version 1.62.0

New feature:

1. Color Adjustment has been added.

Improvement:

1. Accuracy in automatic rotation has been improved in scanning business-card-size documents with background pattern in color under the setting where [Page] under [Rotation] is set to [Automatic].

Service Update 7

Version 1.52.0.6553

Improvement:

1. Low resolution images have less noise now.

Corrected issue:

1. Minor errors have been modified.

Version 1.46.0.5900

Corrected issue:

1. Minor errors have been modified.